
Database First koppling


Först måste du säkerställa att du använder .Net Framework 4.5.

I ditt projekt, högerklicka på ditt projekt -> välj properties
se bilden nedan:





Nu lägg till Entity Data Model genom att högerklicka på projektet i projekt lösningen (solution explorer) -> "Add" -> Klicka på "New Item" och välj "ADO.NET Entity Data Model" från popupen, Ge det nya objektet lämpligt namn och klicka på "Add" knappen.





Eftersom vi vill ha en database first modell så skall vi välja "Generate from database" eller om du har en lite äldre version av VS så kan det stå "EF Designer from database"

Entity Data Model Wizard							
	Choose Model Contents						
What should the model contain?							
Generate from database	17						
Creates an entity model from a database. Object-layer code is generated from the model. This option also lets you specify the database connection, settings for the model, and database objects to include in the model.							
	< Previous Next > Finish Cancel						



Vi skall skapa upp en ny koppling, efter vi klickat **new** kommer sedan frågan om vilken version av Entity Framework som du vill använda, då jag upplevt en del problem med 6.0 (som det finns en del buggar i) så använder jag 5.0 istället.

	Entity Data Model Wizard	х
Choo	ose Your Data Connection	
Which data conn	ection should your application use to connect to the database?	
	∨ New Connection	
to the database. S	tring appears to contain sensitive data (for example, a password) that is required to conne toring sensitive data in the connection string can be a security risk. Do you want to includ in the connection string?	
O No, exclu	de sensitive data from the connection string. I will set it in my application code.	
O Yes, inclu	de the sensitive data in the connection string.	
Entity connection	string:	
		^
✓ Save entity cor	nection settings in App.Config as:	
	< Previous Next > Finish Cancel	



1. Välj datakälla (i mitt fall MS SQL Server)

2. Skriv in server namn (kan behövas att klicka på refresh)

3. Välj databas


4. Testa kopplingen

5. Klicka OK

		Connectio	n Properti	es	?	x
	nter information to hoose a different da			source or c	lick "Change'	to
	Data source:				1	
	Microsoft SQL Serve	r (SqlClient)			Change	
9	Server name: 2					
	devel			~	Refresh	
	Log on to the serve	er				
	Use Windows A	Authentication				
	O Use SQL Server	Authentication				
	User name;					
	Password:					1
		Save my passv	vord			
	Connect to a datab					
	2					
	Select or cincel	a uatabase nume)		1
	O Attach a datab				<u>_</u>	_
	O Attach a datab	ase file:			Browse	1
	Logical name:				Drowse	
	Logicarname					1
ļ				_		
	4			5	Advanced	
	Test Connection			ОК	Cancel	



Låt default värdena vara och klicka next





- Se till att klicka i rutorna som pilarna visar
- Skulle din databas även ha vyer eller stored procedures kan du även välja dessa rutor

